

How-Tos

Wing IDE Personal

Wingware
www.wingware.com

Version 3.2.2
October 26, 2009

This is a collection of HOW-TOs designed to make it easier to get started using Wing on certain platforms with special requirements and with specific tools and libraries for GUI, web, and other types of development.

Contents

Wing IDE Quick Start Guide

- [Install Python and Wing IDE](#)

- [Set up a Project](#)

- [Key Features](#)

- [Related Documents](#)

Wing IDE for OS X

- [Font Size Issues](#)

- [Keyboard Setup Tips](#)

- [Clipboard Problems](#)

- [Changing Display Themes](#)

- [Using other Fonts](#)

- [Finding WINGHOME](#)

- [Mouse Buttons](#)

- [64-bit Python](#)

- [Window Focus](#)

- [Setting up SSH](#)

- [Known Problems](#)

- [Related Documents](#)

Using Wing IDE with IronPython

- [Related Documents](#)

How-Tos for Web Development

4.1. Using Wing IDE with Turbogears

- [Installing Turbogears](#)

- [Configuring Turbogears 1.x to use Wing](#)

- [Configuring Turbogears 2.x to use Wing](#)

- [Notes for Turbogears 1.x](#)

- [Notes for Turbogears 2.x](#)

- Related Documents
- 4.2. Using Wing IDE with Django
 - Installing Django
 - Debugging Django with Wing
 - Launching from Wing
 - Managing Exceptions
 - Debugging with Auto-reload
 - Related Documents
- 4.3. Using Wing IDE with Zope
 - Upgrading from earlier Wing versions
 - Quick Start on a Single Host
 - Starting the Debugger
 - Test Drive Wing IDE
 - Setting Up Auto-Refresh
 - Setting up Remote Debugging
 - Trouble Shooting Guide
 - Related Documents
- 4.4. Using Wing IDE with Plone
 - Performance Hints
 - Related Documents
- 4.5. Using Wing IDE with the Google App Engine
 - Configuring the Environment
 - Debugging Your Application
 - Fixing Debug Probe
 - Using Django
 - Related Documents
- 4.6. Using Wing IDE with web2py
 - Introduction
 - Setting up a Project
 - Debugging
 - Setting Run Arguments
 - Exception Reporting
 - Better Static Auto-completion
 - Related Documents
- 4.7. Using Wing IDE with mod_wsgi
 - Debugging Setup

[Disabling stdin/stdout Restrictions](#)

[Related Documents](#)

4.8. [Using Wing IDE with mod_python](#)

[Quick Start](#)

[Example](#)

[Notes](#)

[Related Documents](#)

4.9. [Using Wing IDE with Paste and Pylons](#)

[Installing Paste and/or Pylons](#)

[Debugging in Wing IDE](#)

[Debugging Mako Templates](#)

[Related Documents](#)

4.10. [Using Wing IDE with Webware](#)

[Introduction](#)

[Setting up a Project](#)

[Starting Debug](#)

[Related Documents](#)

4.11. [Debugging Web CGIs with Wing IDE](#)

[How-Tos for GUI Development](#)

5.1. [Using Wing IDE with wxPython](#)

[Installation and Configuration](#)

[Test Driving the Debugger](#)

[Using a GUI Builder](#)

[Related Documents](#)

5.2. [Using Wing IDE with PyGTK](#)

[Installation and Configuration](#)

[Auto-completion and Source Assistant](#)

[Using a GUI Builder](#)

[Details and Notes](#)

[Related Documents](#)

5.3. [Using Wing IDE with PyQt](#)

[Installation and Configuration](#)

[Test Driving the Debugger](#)

[Using a GUI Builder](#)

[Tips for Keeping the Debug Process Responsive](#)

[Related Documents](#)

[5.4. Using Wing IDE with matplotlib](#)

[Working in the Python Shell](#)

[Related Documents](#)

How-Tos for Other Libraries

[6.1. Using Wing IDE with Twisted](#)

[Installing Twisted](#)

[Debugging in Wing IDE](#)

[Related Documents](#)

[6.2. Using Wing IDE with Cygwin](#)

[Introduction](#)

[Related Documents](#)

[6.3. Using Wing IDE with pygame](#)

[Debugging pygame](#)

[Related Documents](#)

[6.4. Using Wing IDE with Blender](#)

[Introduction](#)

[Related Documents](#)

[6.5. Using Wing IDE with scons](#)

[Debugging scons](#)

[Related Documents](#)

[6.6. Handling Large Values and Strings in the Debugger](#)

[6.7. Debugging C/C++ and Python together](#)

[6.8. Debugging Extension Modules on Linux/Unix](#)

[Preparing Python](#)

[Starting Debug](#)

[Tips and Tricks](#)

[6.9. Debugging Code with XGrab* Calls](#)

[6.10. Debugging Non-Python Mainloops](#)

[6.11. Debugging Code Running Under Py2exe](#)

Wing IDE Quick Start Guide

This is a minimalist guide for those wanting to get started with Wing IDE as quickly as possible. For a more in-depth introduction, try the **Tutorial**.

Also available: Quick start guides specifically for **OS X installation**, **Zope**, **Plone**, **Turbogears**, **Django**, **wxPython**, **PyGTK** **PyQt**, **Debugging Web CGIs**, **mod_python**, **PyGame**, and **many others**

We welcome feedback and bug reports, both of which can be submitted directly from Wing IDE using the Submit Feedback and Submit Bug Report items in the Help menu, or by emailing us at [support at wingware.com](mailto:support@wingware.com).

Install Python and Wing IDE

Both Python and Wing IDE must be installed. The Wing IDE executable is called `wing-personal13.2`. See **Installing, Running the IDE**, and **Installing your License** for details.

Set up a Project

Wing starts up initially with a blank Default Project. To get the most out of Wing, you must set up your project as follows:

- Use **Add Directory** and other items in the **Project** menu to add source files to the project.
- Use **Project Properties** in the **Project** menu to specify **Python Path** and in some cases select the specific version of Python for use with your project. These two steps tell Wing how to resolve imports in your code, so it can discover and

analyze your source base. This powers Wing's source browser, auto-completer, source assistant (in Wing Pro only), and code navigation features. It is also used for the debugger.

- Save your project to disk.

Note: Depending on the size of the code base you have added to your project, Wing may consume considerable CPU time for up to several minutes analyzing your source code. Once this is done, Wing should run with a snappy and responsive interface even on slower machines. If not, please let us know.

See **Debug Properties** and **Source Code Analysis** for details.

Key Features

You are now ready to start coding and debugging. Most of Wing's features are readily evident from the user interface. The **Wing Tips** tool provides useful usage hints.

These are the features you should be sure to try while evaluating Wing IDE:

- *Configurable Key Bindings* -- Wing can emulate Visual Studio, VI/Vim, Emacs, and Brief key bindings, selected with the editor **Personality** preference.
- *Configurable Tab Key* -- Wing maps the tab key to Indent To Match by default for Python and Increase Indent for other files. This can be changed from the **Tab Key Action** preference.
- *Auto-completion and Source Assistant* -- Wing's editor and the **Source Assistant** tool (in Wing Pro only) provide context-appropriate completion options and documentation as you edit your code. The auto-completer uses Tab by default for completion, but this can be changed in the **Completion Keys** preference.
- *Customizable User Interface* -- Many options are available from **Preferences**, and you can split tools panels and move around the tools within them. Right click on the notebook tabs for options, or use the **Windows** menu to create tools in separate windows. Your configuration is remembered in your project.
- *Goto-definition* -- Available from the toolbar, **Source** menu, and by right-clicking on symbols in the editor.
- *Source Index* -- Quick access to other parts of a source file from the menus at the top of the source editor.

- *Mini-search* -- Wing's powerful keyboard-driven search and replace facility is available from the **Edit** menu. Using the keyboard equivalents given in the menu, bring up the search entry area at the bottom of the screen, type in a search string, then repeat the key bindings for repeated search forward/backward.
- *Search Managers* -- Provide single and multi-file, wild card, and regular expression search and replace. Available as **Search** and **Search in Files** in the tools area.
- *Python Shell* -- This **Python command prompt** lets you try out code in a sandbox process kept isolated from Wing IDE and your debug process.
- *Basic Debugging* -- Set a breakpoint and start debugging. You can use the **Stack Data** tools to inspect or change program data. Wing distinguishes between fatal and non-fatal exceptions at the time they are raised, allowing you to inspect live program state more often. Debug process I/O is shown in the **integrated I/O** tool (or optionally in an external console).

Related Documents

Wing IDE provides many other options and tools. For more information:

- **Wing IDE Tutorial**, a detailed guided tour for Wing IDE.
- **Wing IDE Reference Manual**, which describes Wing IDE in detail.
- **OS X Quickstart**
- **How-tos for using Wing with common packages**

Wing IDE for OS X

Wing IDE uses X windows on OS X, but support for X is not by default part of all versions of OS X. Thus you also need to obtain and install an X server and X Window manager. There are a number of options for this:

- (1) For OS X 10.5, we recommend using the latest version of [XQuartz](#). This may contain fixes not found in the version on your installation disks.
- (2) [Apple's X11 Server for OS X](#) is among the fastest and best integrated options. It includes both the X Server and a native Aqua window manager, although you can replace the default window manager with your favorite if you wish. Apple X11 Server comes with OS X 10.3 and later, but is not installed by default and must be installed separately, usually from Install Disk #2 (but location varies by exact version of the OS). Sometimes the installer is hidden by default so you'll need to scroll down in the Finder window for the installation disk to find it. For OS X 10.3, X11 is also available as downloadable package from Apple's website, but this version will not work with OS X 10.4. If all else fails, search on your install disks for X11User.pkg, which is the package to install.
- (3) [XDarwin](#) (1.1 or later) can be used together with the window manager of your choice. [Window Maker](#) is one that users have reported as working well. [OroborOSX](#) (0.75a4r2 or later) also works but can be quite slow in comparison with other options (as of 0.8 preview 2). Note that for some versions of OroborOSX, you need to unpack both the top-level OroborOSX tar file and the XDarwin.tar file located inside the installation.

Once this is set up, you're ready to install Wing IDE. Just download [Wing IDE](#), double click on the disk image, and move its contents place on your disk (or, you can just run Wing directly from the disk image).

Next make sure your X Windows server chosen above is running and set up to allow connections from X clients on :0.0. Wing will automatically start Apple X11 Server if it is present and not yet running.

Then double click on the Wing IDE app. The first time you start Wing, it will ask you to accept the license agreement and will ask for a license. Use the first (default) option in the dialog that appears to obtain a 10 day trial license (this can be renewed twice when the trial period expires).

At this time, Wing will create a **User Settings Directory** in `~/.wingpersonal3`, which is used to store preferences and other settings.

The location of Wing's internal application contents folder is referred to as `WINGHOME`. For example if you unpacked Wing into `/Applications/Wing` then `WINGHOME` will be `/Applications/Wing/WingIDE.app/Contents/MacOS`.

To start Wing from the command line, execute `wing` located in `WINGHOME` (`/Applications/Wing/WingIDE.app/Contents/MacOS/wing` in the above example). When you do this, you may need to set your `DISPLAY` environment variable to point to your X Server (for example `setenv DISPLAY :0.0`).

See the **Tutorial** and **Wing IDE Quickstart Guide** for additional information on getting starting with Wing IDE.

Font Size Issues

If you are using XQuartz 2.3.2 or later, the default dots-per-inch (dpi) reported by the X11 server is 96 instead of the earlier default of 72. Depending on your display, this may lead to poor initial font size choices. You can change the font size in Wing's Preferences (in the Edit menu) or in extreme cases where the font is entirely unreadable, you can set the X11 server's reported dpi as follows from the xterm:

```
defaults write org.x.X11 dpi -int 75
```

For additional information on this and other issues, see the [XQuartz X11 Users FAQ](#).

Keyboard Setup Tips

Wing starts with a keyboard mapping that emulates the most commonly used key standards on the Macintosh. This mapping will not work properly unless you uncheck the "Enable Keyboard Shortcuts under X11" preference in Apple X11 Server configuration (this was called "Enable Key Equivalents under X11" in older versions). Wing will warn when this option is checked, but may fail to do so under other X11 server software. Wing also tries to detect if an Apple keyboard is in use, but you may need to set the **Apple Keyboard** preference to `yes` or `no` if the detection fails.

You can alter keyboard mapping (for example, to use Emacs bindings instead) with the **Personality** preference, or change individual key mappings with the **Custom Key Bindings** preference. If you do use a keyboard personality other than the OS X personality, you may want to map the option or command key to the Alt modifier using the **Global X11 Alt Key** preference. The option key should be used only if you don't need the option key to enter individual characters. Note that this preference affects all X11 applications, not just Wing. It may also affect whether the **Custom Key Bindings** preference will accept **Command** as a key modifier.

Under OS X 10.4 (Tiger), the option/compose key used to enter accented and other foreign characters will not work because of changes in the Apple X11 applications. To fix this, enable the **Fix Option key bug in Tiger (OS X 10.4)** preference. This will affect all X11 applications, not just Wing.

If you are running other X11 applications and want to work around this bug yourself, you'll want to either enable the XKEYBOARD extension on the X11 server or use xmodmap to assign the Mode_Switch key to a modifier other than mod1. The xmodmap script that Wing runs when the **Fix Option key bug in Tiger (OS X 10.4)** preference is enabled is `${WINGHOME}/resources/osx/fix-tiger-mode-switch.xmodmaprc`. The script removes Mode_Switch from mod1 and adds it to mod5 and is run only if the preference is enabled and xmodmap reports that Mode_Switch is assigned to mod1.

If the X11 Application "Use the system keyboard layout" preference is enabled, then the X11 server may modify its keyboard mapping when the system keyboard changes. You may need to disable this preference or restart Wing after the keyboard layout changes because Wing will not re-apply the fix after the X11 keyboard changes. This should only be an issue if you change keyboard layouts while Wing is running.

Depending on the version of Apple X11 Server and possibly other factors, any of the keyboard preference changes made in X11 Server configuration or those Wing preferences indicated above as affecting all X11 applications may require restarting both Wing and Apple X11 Server before they work properly.

If OS X intercepts F keys (such as F1, and F9), you may also need to change the settings in the OS X System Settings, under Keyboard/Mouse.

Clipboard Problems

As noted above, clipboard (copy/paste) confusion can occur if the Apple X11 or XQuartz preference "Enable Keyboard Shortcuts under X11" (this was called "Enable Key Equivalents under X11" in older versions) is turned on.

On OS X 10.5 with XQuartz you may also see the clipboard get overwritten with the OS

X / system clipboard whenever Wing shows a popup window, such as an auto-completer. To prevent this, turn off the Focus on New Windows preference in the X11 Preferences, under the Windows tab.

Changing Display Themes

Although Wing is not a native OS X application, it starts up with a display theme that tries to match the OS X look and feel (font size often needs to be altered from the **Display Font/Size** preference). Additional display themes can be selected from the **Display Theme** preference.

It is also possible to download [other themes for GTK2](#) and place them into `Contents/MacOS/bin/gtk-bin/share/themes` inside your Wing IDE installation. Once this is done and Wing is restarted, they will show up in the **Display Theme** preference.

One nice OS X like theme is [AquaX](#), currently not included with Wing because we cannot redistribute it under its licensing.

Note that only themes that do not use a theme engine or use one of those in `/bin/gtk-bin/lib/gtk-2.0/2.4.0/engines` in your Wing installation will work with Wing IDE. We cannot make any guarantees for performance or results when using themes not included with Wing IDE, although Aqua X is known to work well.

Using other Fonts

The X11-provided set of fonts may not be adequate for all languages and may not be able to display all the needed glyphs. If none of the provided fonts works for you, make a directory `~/.fonts` (`.fonts` in your home directory) and then selectively copy `.ttf` fonts over from `/System/Library/Fonts` and/or `/Library/Fonts`. They should appear in the list of choices when you restart Wing. **Important:** Do this one or a few fonts at a time since some of the `.ttf` fonts will hang Wing at startup.

Finding WINGHOME

When using the **Zope Support Module** or following instructions that refer to `WINGHOME` note that `WINGHOME` is defined as the location of the `wing` executable, which on Mac OS X is inside the `Contents/MacOS` folder of the Wing IDE app folder. E.g., if you unpacked Wing into `/Applications/Wing` then `WINGHOME` will be `/Applications/Wing/WingIDE.app/Contents/MacOS`.

Mouse Buttons

Right-click for menus by holding down the Option/Alt key while clicking. Middle-click by holding down the Control key while clicking. These defaults can be changed in your X11 server's preferences. For example, under Apple X11 Server, change so Option/Alt is button two and Control is button three with this command:

```
defaults write com.apple.x11 fake_button2 option
defaults write com.apple.x11 fake_button3 control
```

Or change so that Option/Alt is button two and Apple/Command is button three:

```
defaults write com.apple.x11 fake_button2 option
defaults write com.apple.x11 fake_button3 command
```

Then restart the X11 Server.

64-bit Python

On newer 64-bit OS X systems you will need to set the following in your Project Properties in Wing, in the Environment property, before the debugger or Python Shell will work:

```
VERSIONER_PYTHON_PREFER_32_BIT=yes
```

This causes Python to run in 32-bit mode so it will work with Wing's debugger.

Window Focus

You can configure Apple X11 Server to automatically transfer focus to the window the mouse pointer is over, or to pass through the click that is used to bring focus to the window so it is also processed by the application.

To move focus with the mouse pointer:

```
defaults write com.apple.x11 wm_ffm true
```

To pass through the focus click:

```
defaults write com.apple.x11 wm_click_through -bool true
```

You must restart Apple X11 changing either of these configurations before they take effect.

Other configuration options like this can be obtained by looking in the manual pages for quartz-wm and Xquartz:

```
man quartz-wm  
man Xquartz
```

Setting up SSH

If you plan to use revision control in Wing and you connect to your server via ssh, you will either want to launch Wing from the command line after doing `ssh-agent bash` followed by `ssh-add` or make use of a utility like [SSHKeyChain](#). For details see **Setting up SSH**.

Known Problems

At least some versions of the MacPorts packaging of Python are known not to work with Wing's debugger because it contains an `_md5` module that won't load. To work around this, use a different distribution of Python instead.

The copy of Python shipped with OS X does not include source files for the standard libraries, so Wing's editor will not offer autocompletion values for those modules. To work around this, use a copy of Python installed from the standard source distribution.

There is no way to control-click on a Mac, so control-left-click for the goto-definition feature doesn't work. Instead, use Goto Selected Symbol from the Source menu instead; this works relative to position of the insertion cursor in the current editor and can be accessed by the key binding shown in the Source menu.

Please send bug reports to [bugs at wingware.com](mailto:bugs@wingware.com).

Related Documents

- **Wing IDE Quickstart Guide**, which contains additional information about getting started with Wing IDE.
- **Other How-Tos**, for getting started with Wing IDE and specific tools.
- **Wing IDE Reference Manual**, which describes Wing IDE in detail.

Using Wing IDE with IronPython

[Wing IDE](#) is an integrated development environment for the Python programming language. Wing can be used to speed up the process of writing code for [IronPython](#), which is an implementation of Python for the .NET runtime.

For more information on setting up Wing IDE with IronPython, see [IronPython and the Wing IDE: Using the Wing Python IDE with IronPython](#). This article provides a script to help with setting up auto-completion for the .NET framework, and some information on how to get Wing to execute your code in IronPython. It was written by Michael Foord, co-author of the book [IronPython in Action](#).

Related Documents

Wing IDE provides many other options and tools. For more information:

- **Wing IDE Reference Manual**, which describes Wing IDE in detail.
- [IronPython home page](#), which provides links to documentation.
- **Wing IDE Tutorial**
- **Wing IDE Quickstart Guide** which contains additional basic information about getting started with Wing IDE.

How-Tos for Web Development

The following How-Tos provide tips and short cuts for using a number of popular web development frameworks with Wing IDE.

4.1. Using Wing IDE with Turbogears

[Wing IDE](#) is an integrated development environment for the Python programming language. Wing can be used to speed up the process of writing and debugging code that is written for [Turbogears](#), a powerful web development system.

In order to debug Turbogears applications, you will need Wing 3.0 or later, since earlier versions did not support multi-threaded debugging.

Note that some parts of this document are for Turbogears 1.x only, and others (as indicated) for Turbogears 2.x only.

Installing Turbogears

The [Turbogears website](#) provides complete instructions for installing Turbogears. The procedure varies slightly by OS. See also the Notes section below.

Configuring Turbogears 1.x to use Wing

This section assumes your Turbogears 1.x project is called `wingtest`. If not, substitute your project name in the following instructions.

- Go into the Turbogears instance directory `wingtest` and run Wing

- Add your instance directory to the project and save it as `wingtest.wpr`. There is no need to add all of Turbogears to the project; just the instance should suffice.
- Open `start-wingtest.py` in Wing and set it as main debug file from the **Debug** menu
- Edit `start-wingtest.py` and add the following before the server is started:

```
import os
import cherrypy
if os.environ.has_key('WINGDB_ACTIVE'):
    cherrypy.config.update({'autoreload.on': False})
```

This is needed to prevent creation of a sub-process controlled by the auto-restarter, which breaks debugging since Wing's debugger will not be running in the sub-process. If you omit this step, the symptom will be failure to stop on any breakpoints in your Turbogears application.

- Set a breakpoint on the `return` line of `Root.index()` in your `controllers.py` or somewhere else you know will be reached on a page load
- Start debugging in Wing from the toolbar or debug icon. If Wing issues a warning about `sys.settrace` being called in `DecoratorTools` select **Ignore this Exception Location** in the **Exceptions** tool in Wing and restart debugging. In general, `sys.settrace` will break *any* Python debugger but Wing and the code in `DecoratorTools` both take some steps to attempt to continue to debug in this case.
- Bring up the **Debug I/O** tool in Wing and wait until the server output shows that it has started
- Load `http://localhost:8080/` or the page you want to debug in a browser
- Wing should stop on your breakpoint. Be sure to look around a bit with the **Stack Data** tool and the **in Wing Pro** the **Debug Probe** (a command line that works in the runtime state of your current debug stack frame).

Configuring Turbogears 2.x to use Wing

Turbogears 2.0 changed some things about how Turbogears instances are packaged and launched, so the configuration is different than with Turbogears 1.x.

This section assumes your Turbogears 2.x project is called `wingtest`. If not, substitute your project name in the following instructions.

- Go into the Turbogears instance directory `wingtest` and run Wing

- Add your instance directory to the project and save it as `wingtest.wpr`. There is no need to add all of Turbogears to the project; just the instance should suffice.
- Add also the `paster` to your project. Then open it and set it as main debug file from the `Debug` menu
- Open up the Python Shell tool and type `import sys` followed by `sys.executable` to verify whether Wing is using the Python that will be running Turbogears. If not, open `Project Properties` and set the `Python Executable` to the correct one.
- Next right click on `paster` and select `File Properties`. Under the `Debug` tab, set `Run Arguments` to `serve development.ini` (do not include the often-used `--reload` argument, as this will interfere with debugging). Then also set `Initial Directory` to the full path of `wingtest`.
- Set a breakpoint on the `return` line of `RootController.index()` in your `root.py` or somewhere else you know will be reached on a page load
- Start debugging in Wing from the toolbar or debug icon. If Wing issues a warning about `sys.settrace` being called in `DecoratorTools` select `Ignore this Exception Location` in the `Exceptions` tool in Wing and restart debugging. In general, `sys.settrace` will break *any* Python debugger but Wing and the code in `DecoratorTools` both take some steps to attempt to continue to debug in this case.
- Bring up the `Debug I/O` tool in Wing and wait until the server output shows that it has started
- Load `http://localhost:8080/` or the page you want to debug in a browser
- Wing should stop on your breakpoint. Be sure to look around a bit with the `Stack Data` tool and in Wing Pro the `Debug Probe` (a command line that works in the runtime state of your current debug stack frame).

Notes for Turbogears 1.x

Turbogears 1.x will install itself into whichever instance of Python runs the installer script, and only certain versions of Python work with a given version of Turbogears.

If you want to avoid adding Turbogears to an install of Python that you are using for other purposes, you can install Python to a new location and dedicate that instance to Turbogears. On Linux, this can be done as follows (assuming you create `/your/path/to/turbogears` as the place to install):

- In a Python source dist do:

```
./configure --prefix=/your/path/to/turbogears
make
make install
```

- Download `tgsetup.py` (or from the Turbogears website)
- Change to `/your/path/to/turbogears`
- Run `bin/python tgsetup.py --prefix=/your/path/to/turbogears` (this works in Turbogears 1.0.5 but in older versions you may need to edit `tgsetup.py` to replace `/usr/local/bin` with `/your/path/to/turbogears/bin`.)
- Run `bin/tgadmin quickstart`
- Enter project name `wingtest` and defaults for the other options

Similar steps should work on Windows and OS X.

Notes for Turbogears 2.x

Turbogears 2.x uses `virtualenv` to separate what it installs from your main Python installation so in most cases you can install Turbogears 2.x using an installation of Python that you also use for other purposes. If, however, a clean or separate Python installation is desired, you can install Python to a new location and dedicate that instance to Turbogears. On Linux, this can be done as follows (assuming you create `/your/path/to/turbogears` as the place to install):

- In a Python source dist do:

```
./configure --prefix=/your/path/to/turbogears
make
make install
```

- Then install `easy_install` by running its setup script with the Python at `/your/path/to/turbogears/bin/python`.
- Whenever the Turbogears installation instructions call for invoking `easy_install` use the one in `/your/path/to/turbogears/bin`

Similar steps should work on Windows and OS X.

Related Documents

Wing IDE provides many other options and tools. For more information:

- **Wing IDE Reference Manual**, which describes Wing IDE in detail.
- [Turbogears home page](#), which provides links to documentation.
- **Wing IDE Quickstart Guide** which contains additional basic information about getting started with Wing IDE.

4.2. Using Wing IDE with Django

“Having to debug Django issues is almost enjoyable with the new debugger support.” -- *Doug Napoleone, Oct 2007*

[Wing IDE](#) is an integrated development environment for the Python programming language. Wing can be used to speed up the process of writing and debugging code that is written for [Django](#), a powerful web development system.

In order to debug Django applications, you will need Wing 3.0 or later, since earlier versions did not support multi-threaded debugging.

Note: This document contains information obtained from users of Wing IDE. Its accuracy has not yet been verified by Wingware.

Installing Django

The [Django website](#) provides complete instructions for installing Django.

Debugging Django with Wing

By default, Django runs in an environment that spawns and automatically re-launches a sub-process for servicing web requests. This is used to automatically restart the server if for some reason it crashes. However, this does not work with Wing’s debugger if you launch Django from Wing, since the debugger has no way to cause the sub-process to be debugged when it is started by the main process.

There are two ways to debug Django code: Either configure Django so it can be launched by Wing's debugger, or cause Django to attach to Wing on the fly as code that you wish to debug is executed.

Launching from Wing

When Django is launched from Wing, it must be configured to avoid auto-reload and other options that break the debugger.

Newer versions of Django include a `--noreload` option that you can pass to the `manage.py` or `django-admin.py` scripts to turn off the auto restart feature of Django.

The typical way to do all this is to set the `manage.py` file as the primary debug file in Wing and give it the following **Run Arguments** via the **Debug** properties tab in the **File Properties** dialog:

```
runserver --noreload
```

Other options can be added here as necessary for your application.

Some versions of Django may also require adding `--settings=devsettings` to the arguments for `runserver`, in order for debugging to work. If Wing is not be able to stop on any breakpoints, try adding this.

In older versions of Django, the `--noreload` option does not exist. The only way to solve the problem there is to make a modification to the code to prevent launching of a sub-process, or to use the alternative method described below.

Managing Exceptions

Some versions of Django raise `NameError` and `UnboundLocalError` exceptions as part of their normal operation. By default, Wing reports all exceptions of these types, since they often indicate a program error even if caught. You can ignore the particular instances of these in Django with the **Ignore this Exception Location** checkbox in the **Exceptions** tool, or by removing these from the **Debugger / Exceptions / Always Report** preference.

Debugging with Auto-reload

Another method of debugging Django is to use `wingdbstub.py` to initiate debugging when Django is started from outside of Wing IDE. This will allow Django to restart

automatically after code changes and to automatically reconnect the debugger to Wing IDE as needed.

This is done by placing a copy of `wingdbstub.py`, which is located in your Wing IDE installation directory, in the top of the Django directory, where `manage.py` is located. Next, place the following code into files you wish to debug:

```
import wingdbstub
```

Then make sure that the **Enable Passive Listen** preference is enabled in Wing and start Django. The Django process should connect to Wing IDE and stop at any breakpoints set after the `import wingdbstub`.

When code is changed, just save it and Django will restart. The debugger will reconnect to Wing IDE once you request a page load in your browser that leads to one of your `import wingdbstub` statements.

Related Documents

Wing IDE provides many other options and tools. For more information:

- **Wing IDE Reference Manual**, which describes Wing IDE in detail.
- [Django home page](#), which provides links to documentation.
- **Wing IDE Quickstart Guide** which contains additional basic information about getting started with Wing IDE.

4.3. Using Wing IDE with Zope

<p>“The best solution for debugging Zope and Plone” -- <i>Joel Burton, Member, Plone Team, Jul 2005</i></p>
--

[Wing IDE](#) can be used to develop and debug Python code running under Zope2 or Zope3, including Products, External Methods, file system-based Scripts and Zope itself. It is also useful for Zope-based frameworks like [Plone](#) (see **Plone Quickstart**).

Wing provides auto-completion, call tips, and other features that help to write, navigate, and understand Zope code. Wing’s debugger can work with Zope’s code reloading features to achieve a very short edit/debug cycle.

Note: This guide is for Zope2 users. If you are using Zope3, please try [z3wingdbg](#) by Martijn Pieters or refer to **Debugging Externally Launched Code** in the users manual to set up Zope3 debugging manually.

Limitations: Wing IDE cannot debug DTML, Page Templates, ZCML, or Python code that is not stored on the file system.

Security Warning: We advise against using the WingDBG product on production web servers. Any user connected to the Wing IDE debugger will (unavoidably) have extensive access to files and data on the system.

Upgrading from earlier Wing versions

If you are upgrading from an older version of Wing and have previously used Wing with your Zope installation(s), you need to manually upgrade WingDBG in each Zope instance. Otherwise, debugging may fail.

The easiest way to do this is to go to the Zope Control Panel, click on **Wing Debug Service**, and then **Remove** the control panel. Then restart Zope. Next, go into your Wing project's **Extension Tab**, verify that you've got the **Zope Instance Home** set correctly, and press **Apply**. This will offer to re-install WingDBG with the latest version and will configure it to point to the new version of Wing.

Quick Start on a Single Host

To use Wing IDE with Zope running on the same host as the IDE:

- **Install Zope** -- You can obtain Zope from zope.org. Version 2.5.1 or newer will work with Wing.
- **Install Wing IDE** -- You will need [Wing IDE](#) 2.1 or later. See **Installing** for details.
- **Configure Wing IDE** -- Start Wing, create or open the project you wish to use (from the **Project** menu). Then use the **Extensions** tab in **Project Properties** to enable **Zope2/Plone support** and to specify the **Zope2 Instance Home** to use with the project. Wing will find your Zope installation by reading the file `etc/zope.conf` in the provided Zope instance. Once you press **Apply** or **OK** in the **Project Properties** dialog, Wing will ask to install the WingDBG product and will offer to add files from your Zope installation to the project.

If your zope instance is generated by buildout, set the main debug file to the `bin/instance` file (`bin\instance-script.py` on Windows) in your buildout tree by opening the file in Wing and select **Set Current as Main Debug File** in the **Debug** menu. This will set up the effective `sys.path` for the instance.

- **Configure the WingDBG Product** -- Start or restart Zope and log into <http://localhost:8080/manage> (assuming default Zope configuration). The Wing Debugging Service will be created automatically on startup; you can find it under the Control Panel of your server.

Starting the Debugger

Proceed to the Wing Debugger Service by navigating to the Control Panel, then selecting the 'Wing Debugging Service'. Click in the "Start" button. The Wing IDE status area should display "Debugger: Debug process running".

Note that you can configure WingDBG to start and connect to the IDE automatically when Zope is started from the Advanced configuration tab.

Problems? See the Trouble-Shooting Guide below.

Test Drive Wing IDE

Once you've started the debugger successfully, here are some things to try:

Run to a Breakpoint -- Open up your Zope code in Wing IDE and set a breakpoint on a line that will be reached as the result of a browser page load. Then load that page in your web browser using the port number displayed by the Zope Management Interface after you started the debugger. By default, this is 50080, so your URL would look something like this:

```
http://localhost:50080/Rest/Of/Usual/Url
```

Explore the Debugger Tools -- Take a look at these tools available from the Tools menu:

- **Stack Data** -- displays the stack, allows selecting current stack frame, and shows the locals and globals for that frame.
- **Debug Probe (Wing Pro only)** -- lets you interact with your paused debug process using a Python shell prompt

- **Watch** (Wing Pro only) -- watches values selected from other value views (by right-clicking and selecting one of the **Watch** items) and allows entering expressions to evaluate in the current stack frame
- **Modules** (Wing Pro only) -- browses data for all modules in `sys.modules`
- **Exceptions** -- displays exceptions that occur in the debug process
- **Debug I/O** -- displays debug process output and processes keyboard input to the debug process, if any

Continue the Page Load -- When done, select **Start / Continue** from the **Debug** menu or toolbar.

Try Pause -- From Wing, you can pause the Zope process by pressing the pause icon in the toolbar or using **Pause** from the **Debug** menu. This is a good way to interrupt a lengthy computation to see what's going on. When done between page loads, it pauses Zope in its network service code.

Other Features -- Notice that Wing IDE's editor contains a source index and presents you with an auto-completer when you're editing source code. Control-click on a source symbol to jump to its point of definition (or use **Goto Selected Symbol** in the **Source** menu). Wing Pro also includes a **Source Assistant** and **Source Browser**. The **Source Assistant** will display context appropriate call tips and documentation. Bring up the **Source Browser** from the **Tools** menu to look at the module and class structure of your code.

Setting Up Auto-Refresh

When you edit and save Zope External Methods or Scripts, your changes will automatically be loaded into Zope with each new browser page load.

By default, Zope Products are not automatically reloaded, but it is possible to configure them to do so. This can make debugging much faster and easier.

Take the following steps to take advantage of this feature:

- Place a file called `refresh.txt` in your Product's source directory (for example, `Products/MyProductName` inside your Zope installation). This file tells Zope to allow refresh for this product.
- Open the Zope Management Interface.
- Expand the **Control Panel** and **Products** tabs on the upper left.

- Click on your product.
- Select the Refresh tab.
- Check the “Auto refresh mode” check box and press “Change”.
- Make an edit to your product source, and you should see the changes you made take effect in the next browser page load.

Limitations: Zope may not refresh code if you use `import` statements within functions or methods. Also, code that manages to retain references to old code objects after a refresh (for example, by holding the references in a C/C++ extension module) will not perform as expected.

If you do run into a case where auto-reload causes problems, you will need to restart Zope from the Zope Management Interface’s Control Panel or from the command line. Note that pressing the Stop button in Wing only disconnects from the debug process and does not terminate Zope.

Setting up Remote Debugging

Configuring Wing for remote debugging can be complicated, so we recommend using X Windows (Linux/Unix) or Remote Desktop (Windows) to run Wing IDE on the same machine as Zope but display it remotely. When this is not possible, you can set up Wing to debug Zope running on another machine, as described below:

- **Set up File Sharing** -- You will need some mechanism for sharing files between the Zope host and the Wing IDE host. Windows file sharing, Samba, NFS, and ftp or rsync mirroring are all options. For secure file sharing via SSH on Linux, try [sshfs](#).
- **Install Wing on the Server** -- You will also need to install Wing on the host where Zope is running, if it is not already there. No license is needed for this installation, unless you plan to also run the IDE there. If there is no binary distribution of Wing available for the operating system where Zope is running, you can instead install only the debugger libraries by building them from source code (contact Wingware for details).
- **Basic Configuration** -- Follow the instructions for Single-Host Debugging above first if you have not already done so. Then return here for additional setup instructions.
- **Configure Allowed Hosts** -- You will need to add the IP address of the Zope host to the **Allowed Hosts** preference in Wing. Otherwise Wing will not accept your debug connections.

- **Configure File Mapping** -- Next, set up a mapping between the location of the Zope installation on your Zope host and the point where it is accessible on your Wing IDE host. For example, if your Zope host is 192.168.1.1 Zope is installed in /home/myuser/Zope on that machine, and /home/myuser is mounted on your Wing IDE host as e:, you would add a **Location Map** preference setting that maps 192.168.1.1 to a list containing /home/myuser/Zope and file:e:/Zope. For more information on this, see **File Location Maps** and **Location Map Examples** in the Wing IDE manual.
- **Set the Zope Host** -- Go into Project Properties and set the Zope Host to match the host name used in configuring the File Location Map in the previous step. This is used to identify which host mapping should be applied to file names read from the zope.conf file.
- **Modify WingDBG Configuration** -- When debugging remotely, the value given to WingDBG for the Wing Home Directory must be the location where Wing is installed on the Zope host (the default value will usually need to be changed).
- **Check Project Configuration** -- Similarly, the paths identified in Project Properties should be those on the host where Wing IDE is running, not the paths on the Zope host.

Trouble Shooting Guide

You can obtain additional verbose output from Wing IDE and the debug process as follows:

- If Zope or Plone on Windows is yielding a Site Error page with a notFoundError when run under Wing's debugger, you may need to go into the Zope Management Interface and delete the access rule (... accessRule.py ...). Now, Zope/Plone runs on port 8080, does not alter the configuration of port 80, and will work properly with Wing's debug port (50080 by default). If the URL for your front page is <http://localhost:8080/default/front-page>, the Wing IDE debug url will always be the same but with the different port: <http://localhost:50080/default/front-page> (Thanks for Joel Burton for this tip!)
- Go into the Wing Debugging Service in the Zope Management Interface and set **Log file** under the **Configure** tab. Using <stdout> will cause logging information to be printed to the console from which Zope was started. Alternatively, set this to the full path of a log file. This file must already exist for logging to occur.
- Restart Zope and Wing and try to initiate debug.

- Inspect the contents of the log. If you are running Zope and Wing IDE on two separate hosts, you should also inspect the `error-log` file on the Wing IDE host (located in the **User Settings Directory**). It contains additional logging information from the Wing IDE process.

For additional help, send these errors logs to [support at wingware.com](mailto:support@wingware.com).

Related Documents

Wing IDE provides many other options and tools. For more information:

- **Wing IDE Reference Manual**, which describes Wing IDE in detail.
- [Zope home page](#), which contains much additional information for Zope programmers.
- **Quick Start Guide** and **Tutorial** which contain additional basic information about getting started with Wing IDE.

4.4. Using Wing IDE with Plone

“The best solution for debugging Zope and Plone” -- *Joel Burton, Member, Plone Team, Jul 2005*

[Wing IDE](#) is an integrated development environment for the Python programming language. Wing can be used to speed up the process of writing and debugging code that is written for [Plone](#), a powerful web content management system.

Since Plone is based on [Zope](#), setting up Wing IDE with Plone is very similar to setting up Wing IDE with Zope, which is described in detail in the **Zope quickstart guide**. The only difference is that you will download and install Plone instead of Zope. Also, instead of launching Zope only, you will be launching Plone (which on win32 is done with the Plone launcher tool from the Start menu).

Performance Hints

Plone and Zope together contain a very large Python code base. If you **Add Directory** from the **Project** menu to include the entire Plone installation, you will see significant

CPU intensive processing, which can be an issue on slower machines and may take several minutes to complete. Wing should remain responsive during this time but may be sluggish in some cases.

Processing should cease after a period of time and the rest of your Wing IDE session should run at near zero CPU usage, with a snappy and responsive GUI even on slower machines.

Related Documents

Wing IDE provides many other options and tools. For more information:

- **Using Wing IDE with Zope**, which describes how to set up Zope for use with Wing IDE.
- **Wing IDE Reference Manual**, which describes Wing IDE in detail.
- [Plone home page](#), which provides links to documentation.
- **Wing IDE Quickstart Guide** which contains additional basic information about getting started with Wing IDE.
- [Plone Bootcamps](#) offer comprehensive training on Plone using Wing IDE throughout the course. Students learn how to set up and use Wing IDE with Plone.

4.5. Using Wing IDE with the Google App Engine

[Wing IDE](#) is an integrated development environment for the Python programming language. Wing can be used to speed up the process of writing and debugging code that is written for the [Google App Engine](#).

In order to debug Google App Engine applications, you will need Wing 3.1 beta3 or later, since earlier versions were missing some important functionality.

Configuring the Environment

In order for Wing to be able to work with Google App Engine code, you will need to create a project in Wing and set the main debug file to the `dev_appserver.py` located in the top level of the Google SDK directory. This is done with the **Set Main Debug File** item in the **Debug** menu.

Debugging Your Application

You can debug code running under the Google App Engine by selecting **Start / Continue** from the **Debug** menu (or use the run icon in the toolbar) and then specifying your application's directory as the run argument. For example, to run the guestbook demo that comes with the SDK, the run argument would be `"${GOOGLE_APPENGINE_DIR}/demos/guestbook"` where `${GOOGLE_APPENGINE_DIR}` is replaced by the full pathname of the directory the SDK is installed in or an environment variable is set up with the pathname. The quotation marks are needed if the pathname contains a space.

Once the debugger is started, requests may be made with a web browser and breakpoints may be set in any Python file. For example, to break when the main page of the guestbook demo is generated, set a breakpoint in the method `Mainpage.get` in `guestbook.py`. You may edit the Python code for an application while the App Engine is running, and then reload to see the changes.

Note that the **Debugger / Exceptions / Report Exceptions** preference should be set to **When Printed** when working with Google App Engine or Wing will report some additional exceptions that are handled internally when running Google App Engine outside of the debugger.

Fixing Debug Probe

The Debug Probe in Wing requires a few modules that some newer versions of Google App Engine (for example 1.2.4) omit. You can fix the Debug Probe to work properly by changing code in `dev_appserver.py` (the copy located in the `google/appengine/tools` sub-directory, not the one at the top level) to include the `__builtin__` and `imp` modules in those that are included. In version 1.2.4, this is on line 623 where the code should then read:

```
if (module_name in ('codecs', 'encodings', '__builtin__', 'imp') or
```

The necessary changes may vary in other versions of Google App Engine.

Using Django

If you are using the Django via the `app-engine-patch` project, you need to use `manage.py` as your main debug file instead of `dev_appserver.py` and should follow the instructions in the **Django How-To** (except that the `--noreload` option is not supported). In particular, note the need to ignore the `NameError` exception at startup.

Related Documents

Wing IDE provides many other options and tools. For more information:

- **Wing IDE Reference Manual**, which describes Wing IDE in detail.
- [Google App Engine home page](#), which provides links to documentation.
- **Wing IDE Quickstart Guide** which contains additional basic information about getting started with Wing IDE.

4.6. Using Wing IDE with web2py

[Wing IDE](#) is an integrated development environment for the Python programming language. Wing can be used to speed up the process of writing and debugging code that is written for [web2py](#), an open source web development framework.

To get started, refer to the tutorial in the **Help** menu in Wing and/or the **Wing IDE Quickstart Guide**.

Introduction

Wing IDE allows you to graphically debug a web2py application as you interact with it from your web browser. Breakpoints set in your code from the IDE will be reached, allowing inspection of your running code's local and global variables with Wing's various debugging tools. In addition, in Wing IDE Pro, the **Debug Probe** tab allows you to interactively execute methods on objects and get values of variables that are available in the context of the running web app.

There is more than one way to do this, but in this document we focus on an "in process" method where the web2py server is run from within Wing as opposed to attaching to a remote process.

Setting up a Project

In order to debug web2py code, you need the web2py sources. Download and unpack these, then launch Wing and then create a new project from the **Project** menu. Add the web2py directory and go to the **Project** view by right clicking and selecting **Add Directory**. Then right click on the file `web2py.py` in the project view and select **Set As Main Debug File**.

Debugging

Now you can debug web2py by launching it from Wing. Just click on the green **Debug** icon in the toolbar and wait for the web2py console to appear. Enter a password and start the server as usual.

Once web2py is running, open a file in Wing that you know will be reached when you load a page of your web2py application in your web browser. Place a breakpoint in the code and load the page in your web browser. Wing should stop at the breakpoint. Use the **Stack Data** tool or **Debug Probe** (in Wing Pro) to look around.

Notice that the **Debug Probe** is similar to running a shell from web2py (with `python web2py.py -S myApp -M`) but additionally includes your entire context. You can easily inspect or modify variables, manually make function calls, and continue debugging from your current context.

Setting Run Arguments

When you start debugging, Wing will show the **File Properties** for `web2py.py`. This includes a **Run Arguments** field under the **Debug** tab where you can add any web2py option. For example, adding `-a '<recycle>'` will give you somewhat faster web2py startup since it avoids showing the Tk dialogs and automatically opening a browser window. This is handy once you already have a target page in your browser. Run `python web2py.py --help` for a list of all the available options.

To avoid seeing the **File Properties** dialog each time you debug, un-check the “Show this dialog before each run” check box.

Exception Reporting

Skip this section if you are using web2py version 1.62 or newer.

As shipped, web2py version 1.61 and earlier contain a catch-all exception handler to report unexpected errors in your web browser as tickets. This is useful when tracking problems on a live site.

To make debugging more convenient, change the `except Exception, exception:` clause in the definition of `restricted` at the end of the file `src/gluon/restricted.py` in your web2py installation to read as follows:

```
except Exception, exception:
    # XXX Show exception in Wing IDE if running in debugger
```

```

if __debug__ and 'WINGDB_ACTIVE' in os.environ:
    etype, evalue, tb = sys.exc_info()
    sys.excepthook(etype, evalue, tb)
    raise RestrictedError(layer, code, '', environment)

```

Now you will get exceptions reported in Wing's **Exceptions** tool and can conveniently move up or down the stack and inspect the program state at the time of the exception.

Better Static Auto-completion

Working in your code when the debugger is not running by default misses some auto-completion options because of how web2py works. For example, auto-completion after typing `db.` will fail because `db` is not explicitly defined. To fix this, you can add some hints for Wing as follows at the top of the file:

```

# XXX This makes auto-
# completion work; also need to alter Python Path
# XXX in project properties.
if 0:
    import db

```

Then go into **Project properties** in the **Project** menu and add the following path under **Python Path**:

```

/path/to/web2py/src/applications/news/models

```

Replace `/path/to` according to where you unpacked web2py.

Now, typing `db.` should bring up an auto-completer with the contents of `db` even if the debugger is not running.

Related Documents

Wing IDE provides many other options and tools. For more information:

- **Wing IDE Reference Manual**, which describes Wing IDE in detail.
- **Wing IDE Quickstart Guide** which contains additional basic information about getting started with Wing IDE.

4.7. Using Wing IDE with mod_wsgi

Wing IDE is an integrated development environment for the Python programming language. Wing can be used to speed up the process of writing and debugging Python code that is running under `mod_wsgi`.

To get started, refer to the tutorial in the **Help** menu in Wing and/or the **Wing IDE Quickstart Guide**.

Debugging Setup

When debugging Python code running under `mod_wsgi`, the debug process is initiated from outside of Wing IDE, and must connect to the IDE. This is done with `wingdbstub` according to the instructions in the **Debugging Externally Launched Code** section of the manual.

Because of how `mod_wsgi` sets up the interpreter, be sure to set `kEmbedded=1` in your copy of `wingdbstub.py` and use the debugger API to reset the debugger and connection as follows:

```
import wingdbstub
if wingdbstub.debugger != None:
    wingdbstub.debugger.StopDebug()
    wingdbstub.debugger.StartDebug()
```

Note that in some cases you may need to add a short delay between the `StopDebug` and `StartDebug` calls, using `time.sleep(1)`.

Then right click on the bug icon in lower left of Wing's window and make sure that **Passive Listen** is enabled. After that, you should be able to reach breakpoints by loading pages in your browser.

Disabling stdin/stdout Restrictions

In order to debug, may also need to disable the WSGI restrictions on stdin/stdout with the following `mod_wsgi` configuration directives:

```
WSGIRestrictStdin Off
WSGIRestrictStdout Off
```

Related Documents

Wing IDE provides many other options and tools. For more information:

- **Wing IDE Reference Manual**, which describes Wing IDE in detail.
- **Wing IDE Quickstart Guide** which contains additional basic information about getting started with Wing IDE.

4.8. Using Wing IDE with mod_python

[Wing IDE](#) is an integrated development environment for the Python programming language. Wing can be used to debug code that is run by the [mod_python](#) module for the Apache web server. This document assumes mod_python is installed and Apache is configured to use it; please see the installation chapter of the mod_python manual for information on how to install it.

Since Wing's debugger takes control of all threads in a process, only one http request can be debugged at a time. In the technique described below, a new debugging session is created for each request and the session is ended when the request processing ends. If a second request is made while one is being debugged, it will block until the first request completes. This is true of requests processed by a single Python module and it is true of requests processed by multiple Python modules in the same Apache process and its child processes. As a result, it is recommended that only one person debug mod_python based modules per Apache instance and production servers should not be debugged.

Quick Start

- Copy `wingdbstub.py` from the Wing IDE installation directory into either the directory the module is in or another directory in the Python path used by the module.
- Edit `wingdbstub.py` if needed so the settings match the settings in your preferences. Typically, nothing needs to be set unless Wing's debug preferences have been modified. If you do want to alter these settings, see the **Remote Debugging** section of the Wing IDE reference manual for more information.
- Copy `wingdebugpw` from your **User Settings Directory** into the directory that contains the module you plan to debug. This step can be skipped if the module to be debugged is going to run on the same machine and under the same user as Wing IDE. The `wingdebugpw` file must contain exactly one line.

- Insert `import wingdbstub` at the top of the module imported by the `mod_python` core.
- Insert `if wingdbstub.debugger != None: wingdbstub.debugger.StartDebug()` at the top of each function that is called by the `mod_python` core.
- Enable passive listening in Wing by setting the **Enable Passive Listen** preference to true.
- Restart Apache and load a URL to trigger the module's execution.

Example

To debug the `hello.py` example from the Publisher chapter of the `mod_python` tutorial, modify the `hello.py` file so it contains the following code:

```
import wingdbstub

def say(req, what="NOTHING"):
    if wingdbstub.debugger != None:
        wingdbstub.debugger.StartDebug()
    return "I am saying %s" % what
```

And set up the `mod_python` configuration directives for the directory that `hello.py` is in as follows:

```
AddHandler python-program .py
PythonHandler mod_python.publisher
```

Then set a breakpoint on the `return "I am saying %s" % what` line, make sure Wing is listening for a debug connection, and load `http://[server]/[path]/hello.py` in a web browser (substitute appropriate values for `[server]` and `[path]`). Wing should then stop at the breakpoint.

Notes

In some cases, we've seen Wing fail to debug the second+ request to `mod_python`. If this happens, try the following variant of the above code:

```
import wingdbstub
import time

if wingdbstub.debugger != None:
    wingdbstub.debugger.StopDebug()
    time.sleep(2)
    wingdbstub.debugger.StartDebug()
```

This reinitialized debugging with each page load. The `time.sleep()` duration may be shortened, or may need to be lengthened if Wing does not manage to drop the debug connection and initiate listening for a new connection quickly enough.

Related Documents

- [Wing IDE Reference Manual](#), which describes Wing IDE in detail.
- [Mod_python Manual](#), which describes how to install, configure, and use `mod_python`.

4.9. Using Wing IDE with Paste and Pylons

[Wing IDE](#) is an integrated development environment for the Python programming language. Wing can be used to speed up the process of writing and debugging code that is written for [Paste](#) and [Pylons](#) (which is based on Paste).

In order to debug Pylons and Paste applications, you will need Wing 3.0 or later, since earlier versions did not support multi-threaded debugging.

Installing Paste and/or Pylons

The [Pylons website](#) and [Paste website](#) provide complete instructions for installing Pylons or Paste

Debugging in Wing IDE

Paste and Pylons can be set to run in an environment that spawns and automatically relaunches a sub-process for servicing web requests. This is used to automatically restart

the server if for some reason it crashes. However, this does not work with Wing's debugger since the debugger has no way to cause the sub-process to be debugged when it is started by the main process.

To avoid this, do not specify the `--reload` flag for Paste. Place the following in a file that you add to your project and set as the main debug file:

```
from paste.script.serve import ServeCommand
ServeCommand("serve").run(["development.ini"])
```

This may vary somewhat, as necessary for your application.

Debugging Mako Templates

Wing cannot debug Mako templates directly, but it is possible to debug them through the `.py` translation (stored in `data/templates` in the Pylon tree).

Related Documents

Wing IDE provides many other options and tools. For more information:

- **Wing IDE Reference Manual**, which describes Wing IDE in detail.
- [Pylons home page](#), which provides links to documentation.
- [Paste home page](#), which provides links to documentation.
- **Wing IDE Quickstart Guide** which contains additional basic information about getting started with Wing IDE.

4.10. Using Wing IDE with Webware

[Wing IDE](#) is an integrated development environment for the Python programming language. Wing can be used to speed up the process of writing and debugging code that is written for [Webware](#), an open source web development framework.

To get started, refer to the tutorial in the **Help** menu in Wing and/or the **Wing IDE Quickstart Guide**.

Introduction

Wing IDE allows you to graphically debug a Webware application as you interact with it from your web browser. Breakpoints set in your code from the IDE will be reached, allowing inspection of your running code's local and global variables with Wing's various debugging tools. In addition, in Wing IDE Pro, the **Debug Probe** tab allows you to interactively execute methods on objects and get values of variables that are available in the context of the running web app.

There is more than one way to do this, but in this document we focus on an "in process" method where the Webware server is run from within Wing as opposed to attaching to a remote process. The technique described below was tested with **Webware 0.9** and **Python 2.4** on **CentOS Linux**. It should work with other versions and on other OSes as well. Your choice of browser should have no impact on this technique.

Setting up a Project

Though Wing supports the notion of "Projects" for organizing one's work for this debugging scenario you can use the **Default Project** and simply add your source code directory to it by using **Add Directory** from the **Project** menu.

You will also need to specify a **Python Path** in your **Project Properties** with something like following (your actual paths depend on your installation of Webware and OS):

```
/usr/local/lib/Webware-0.9/WebKit:/usr/local/lib/Webware-0.9:/home/dev/mycodebase
```

Note that on Windows, the path separator should be ';' (semicolon) instead. The Webware **MakeAppDir.py** script creates a default directory structure and this example assumes that the source code is nested within this directory.

To debug your **Webware** app you'll actually be running the **DebugAppServer** and not the regular **AppServer**, so you'll need to bring in the **Debug AppServer** and a couple of other files with these steps:

- 1) Copy the **DebugAppServer.py**, **ThreadedAppServer.py**, and **Launch.py** from the **WebKit** directory and put them in the root of the directory that **MakeAppDir.py** created.
- 2) Right click on **Launch.py** in Wing's editor and select the menu choice **File Properties**. Click the **Debug** tab and enter **DebugAppServer.py** in the **Run Arguments** field. If you're using the default project then leave the initial directory and build command settings as they are.

- 3) If you need to modify the version of Python you're running, you can change the **Python Executable** on the **Environment** tab of this debug properties window, or project-wide from the **Project Properties**.
- 4) Optionally, after adding `Launch.py` to the project, use the **Set Main Debug File** item in the **Debug** menu to cause Wing to always launch this file when debug is started, regardless of which file is current in the editor.

Starting Debug

To debug, press the green **Debug** icon in the toolbar. If you did not set a main debug file in the previous section, you must do this when `Launch.py` is the current file.

The file properties dialog will appear. Optionally, deselect **Show this dialog before each run**. If you do this you can access the dialog again later by right clicking on the file in Wing's editor and selecting **Properties**.

Click OK to start the debug process. The **Debug I/O** tool will show output from the Webware process as it starts up. What you will see there depends upon your Webware application and server settings, but you should see some log messages scroll by. If there is a path or other kind of problem as the debugging process proceeds errors will display in the Debug I/O tool or in a pop-up error message in Wing if you have a missing library or run into another unhandled exception.

Once the process has started up, you will be able to access web pages from your browser according to your configuration of Webware, just as you would when running the server outside of Wing.

Now for the fun part -- fire up your browser and go to the home page of your application. Go into the source file for any Python servlet in Wing and set a breakpoint somewhere in the code path that you know will be executed when a given page is requested. Navigate to that page in your browser and you should see the Wing program icon in your OS task bar begin to flash. (You'll see that the web page won't finish loading -- this is because the debugger has control now; the page will finish loading when you continue running your app by pressing the **Debug** icon in the toolbar).

Now you can make use of all of the powerful debugging functionality available in Wing instead of sprinkling your code with print statements.

Related Documents

Wing IDE provides many other options and tools. For more information:

- **Wing IDE Reference Manual**, which describes Wing IDE in detail.
- **Wing IDE Quickstart Guide** which contains additional basic information about getting started with Wing IDE.

4.11. Debugging Web CGIs with Wing IDE

Wing IDE can be used to debug CGI scripts written in Python, even as they are running as the result of a page load from a web browser. To set up your CGIs for debugging with Wing IDE, refer to the **Debugging Externally Launched Code** section of the manual. Pay careful attention to the permissions on files, especially if your web server is running as a different user than the process that is running Wing IDE. You will also need to make sure that the `wingdebugpw` file is referenced correctly as described in the instructions.

The rest of this guide provides some tips specific to the task of debugging CGIs:

(1) If Wing is failing to stop on breakpoints, check whether you are loading a web page that loads multiple parts with separate http requests -- in that case, Wing may still be busy processing an earlier CGI request when a new one comes in and will fail to stop on breakpoints because only one debug process is serviced at a time. This is a limitation in Wing. The work-around is to load specific parts of the page in the browser by entering the URL you wish to debug.

(2) Any content from your CGI script that isn't understood by the web server will be written to the server's error log. Since this can be annoying to search through, it is much easier to ensure that all output, including output made in error, is displayed in your web browser.

To do this, insert the following at the very start of your code, before importing `wingdbstub` or calling the debugger API:

```
print "Content-type: text/html\n\n<html>\n"
```

This will cause all subsequent data to be included in the browser window, even if your normal Content-type specifier code is not being reached.

(3) Place a catch-all exception handler at the top level of your CGI code and print exception information to the browser. The following function is useful for inspecting the state of the CGI environment when an exception occurs:

```
import sys
```

```

import cgi
import traceback
import string

#-----
-----
def DisplayError():
    """ Output an error page with traceback, etc """

    print "<H2>An Internal Error Occurred!</H2>"
    print "<I>Runtime Failure Details:</I><P>"

    t, val, tb = sys.exc_info()
    print "<P>Exception = ", t, "<br>"
    print "Value = ", val, "\n", "<p>"

    print "<I>Traceback:</I><P>"
    tbf = traceback.format_tb(tb)
    print "<pre>"
    for item in tbf:
        outstr = string.replace(item, '<', '&lt;')
        outstr = string.replace(outstr, '>', '&gt;')
        print string.replace(outstr, '\n', '\n'), "<BR>"
    print "</pre>"
    print "<P>"

    cgi.print_environ()
    print "<BR><BR>"

```

(4) If you are using `wingdbstub.py`, you can set `kLogFile` to receive extra information from the debug server, in order to debug problems connecting back to Wing IDE.

(5) If you are unable to see script output that may be relevant to trouble-shooting, try invoking your CGI script from the command line. The script may fail but you will be able to see messages from the debug server, when those are enabled.

(6) If all else fails, read your web browser documentation to locate and read its error log file. On Linux with Apache, this is often in `/var/log/httpd/error_log`. Any errors not seen on the browser are appended there.

(7) Once you have the debugger working for one CGI script, you will have to set up the `wingdbstub` import in each and every other top-level CGI in the same way. Because this can be somewhat tedious, and because the import needs to happen at the start of each file (in the `__main__` scope), it makes sense to develop your code so that all

page loads for a site are through a single entry point CGI and page-specific behavior is obtained via dispatch within that CGI to other modules. With Python's flexible import and invocation features, this is relatively easy to do.

How-Tos for GUI Development

The following How-Tos provide tips and short cuts for using a number of popular GUI development frameworks with Wing IDE.

5.1. Using Wing IDE with wxPython

[Wing IDE](#) is an integrated development environment for the Python programming language. Wing can be used to speed up the process of writing and debugging code that is written for the powerful [wxPython](#) cross-platform GUI development toolkit.

wxPython is a good choice for GUI developers. It is currently available for MS Windows, Linux, Unix, and Mac OS X and provides native look and feel on each of these platforms.

While Wing IDE does not provide a GUI builder for wxPython, it does provide the most advanced capabilities available for the Python programming language, and it can be used with other available GUI builders, as described below.

Installation and Configuration

Take the following steps to set up and configure Wing IDE for use with wxPython:

- Install Python and Wing. You will need a specific version of Python depending on the version of wxPython you plan to use. Check the wxPython [Getting Started Wiki](#) when in doubt. See the generic **Wing IDE Quickstart Guide** for installation instructions.
- Install wxPython. See the wxPython's website [Getting Started Wiki](#) for installation instructions. Note that you need to install the version of wxPython to match your Python version, as indicated on the [download page](#).
- Start Wing from the Start menu on Windows, the Finder or OS X, or by typing `wing-personal3.2` on the command line on Linux or other Posix systems. Once

Wing has started, you may want to switch to reading this How-To from the **Help** menu. This will add links to the functionality of the application.

- Select **Show Analysis Stats** from the Source menu and if the Python version reported there doesn't match the one you're using with wxPython, then select **Project Properties** from the Project menu and use the **Python Executable** field to select the correct Python version.
- Open the wxPython demo into Wing IDE. This may be located within your Python installation at `site-packages/wx/demo/demo.py`, or `Lib/site-packages/wx/demo/demo.py`, or `c:\Program Files\wxPython2.6 Docs and Demos\demo`, or similar location. On Linux it may be part of a separate wx examples package, for example on Ubuntu 6.06 LTS the demo is in the package `wx2.6-examples`, is installed in `/usr/share/doc/wx2.6-examples/examples/wxPython`, and some files in this directory need to be `gunzip`'ed before the demo will work. Once you've opened `demo.py`, select **Add Current File** from the Project menu. If you can't find `demo.py` but have other wxPython code that works, you can also just use that. However, the rest of this document assumes you're using `demo.py` so you will have to adapt the instructions.
- Set `demo.py` as main entry point for debugging using the **Set Main Debug File** item in the Debug menu.
- Save your project to disk. Use a name ending in `.wpr`.

Test Driving the Debugger

Now you're ready to try out the debugger. To do this:

Start debugging with the **Start / Continue** item in the Debug menu. Uncheck the **Show this dialog before each run** checkbox at the bottom of the dialog that appears and select OK.

The demo application will start up. If its main window doesn't come to front, bring it to front from your task bar or window manager. Try out the various demos from the tree on the left of the wxPython demo app.

Important: In earlier wxPython 2.6 versions, a change to the demo code breaks all debuggers by not setting the `co_filename` attribute on code objects correctly. To fix this, change the line that reads `description = self.modules[modID][2]` around line 804 in `demo\main.py` to instead read `description = self.modules[modID][3]` -- Wing will not stop at breakpoints until this is done.

Next open `ImageBrowser.py` (located in the same directory as `demo.py`) into Wing IDE. Set a breakpoint on the first line of `runTest()` by clicking on the dark grey left margin.

Go into the running demo app and select `More Dialogs / ImageBrowser`. Wing will stop on your breakpoint.

Select `Stack Data` from the `Tools` menu. Look around the stack in the popup at the top of the window and the locals and globals shown below that for the selected stack frame. You may see some sluggishness (a few seconds) in displaying values because of the widespread use of `from wx import *` in wxPython code, which imports a huge number of symbols into the globals name space. This depends on the speed of your machine.

Select `Debug Probe` (Wing Pro only) from the `Tools` menu. This is an interactive command prompt that lets you type expressions or even change values in the context of the stack frame that is selected on the `Debugger` window when your program is paused or stopped at an exception. It is a very powerful debugging tool.

Also take a look at these tools available from the `Tools` menu:

- `I/O` -- displays debug process output and processes keyboard input to the debug process, if any
- `Exceptions` -- displays exceptions that occur in the debug process
- `Modules` (Wing Pro only) -- browses data for all modules in `sys.modules`
- `Watch` (Wing Pro only) -- watches values selected from other value views (by right-clicking and selecting one of the `Watch` items) and allows entering expressions to evaluate in the current stack frame

Using a GUI Builder

Wing IDE doesn't currently include a GUI builder for wxPython but it can be used with other tools, such as [Boa Constructor](#), which does provide a GUI builder but doesn't have the raw power of Wing IDE's debugger and source browser.

To use an external GUI builder, **configure Wing to automatically reload files** that are altered by the GUI builder. This is done in Preferences in the `Files Reloading` area.

Then you can run Wing IDE and your GUI builder at the same time, working with both in an almost seamless manner.

A Caveat: Because Python lends itself so well to writing data-driven code, you may want to reconsider using a GUI builder for some tasks. In many cases, Python's introspection features make it possible to write generic GUI code that you can use to build user interfaces on the fly based on models of your data and your application. This can

be much more efficient than using a GUI builder to craft individual menus and dialogs by hand. In general hand-coded GUIs also tend to be more maintainable.

Related Documents

Wing IDE provides many other options and tools. For more information:

- **Wing IDE Reference Manual**, which describes Wing IDE in detail.
- [wxPython Getting Started page](#), which contains much additional information for wxPython programmers.
- **Wing IDE Quickstart Guide** which contains additional basic information about getting started with Wing IDE.

5.2. Using Wing IDE with PyGTK

[Wing IDE](#) is an integrated development environment for the Python programming language. Wing can be used to speed up the process of writing and debugging code that is written for [PyGTK](#) and [GTK+](#), a mature open source GUI development toolkit.

PyGTK is currently available for Linux/Unix, MS Windows, and Mac OS X (requires X11 Server). Like **PyQt** and unlike **wxPython**, PyGTK runs on the same (GTK-provided) widget implementations on all platforms. Themes can be used to approximate the look and behavior of widgets on the native OS. It is also possible to display native dialogs like the Windows file and print dialogs along side GTK windows. While PyGTK does not offer perfect native look and feel, it provides excellent write-once-works-anywhere capability even in very complex GUIs. Wing IDE is itself written using PyGTK.

Other advantages of PyGTK include: (1) high quality anti-aliased text rendering, (2) powerful signal-based architecture that, among other things, allows subclassing C classes in Python, (3) multi-font text widget with embeddable sub-widgets, (4) model-view architecture for list and tree widgets, and (5) a rich collection of widgets and stock icons.

While Wing IDE does not currently provide a GUI builder for PyGTK, it does provide the most advanced capabilities available for the Python programming language and it can be used with other available GUI builders, as described below.

Installation and Configuration

Take the following steps to set up and configure Wing IDE for use with PyGTK:

- Install Python and Wing. See the generic **Wing IDE Quickstart Guide** for installation instructions.
- Install GTK and PyGTK. If you are on Linux, you may already have one or both installed, or you may be able to install them using your distribution's package manager. Otherwise, check out the [gtk website](#) and [pygtk website](#).
- Start Wing from the Start menu on Windows, the Finder or OS X, or by typing `wing-personal3.2` on the command line on Linux other Posix systems. Once Wing has started, you may want to switch to reading this How-To from the **Help** menu. This will add links to the functionality of the application.
- Select **Show Analysis Stats** from the Source menu and if the Python version reported there doesn't match the one you're using with PyGTK, then select **Project Properties** from the Project menu and use the **Python Executable** field to select the correct Python version.
- Add some files to your project, and set the main entry point with **Set Main Debug File** in the **Debug** menu.
- Save your project to disk. Use a name ending in `.wpr`.
- You should now be able to debug your PyGTK application from within Wing. If you see `ImportErrors` on the PyGTK modules, you will need to add **Python Path** in the **Debug** tab of **Project Properties**, accessed from the **Project** menu.

Auto-completion and Source Assistant

To obtain auto-completion options and call signature information in Wing IDE Pro's Source Assistant, you may need to run a script that converts from PyGTK's defs files into Python interface files that Wing's source analyser can read. This is only necessary if you are working with PyGTK significantly different than version 2.7.4, because Wing ships with pre-built interface information for PyGTK 2.7.4. If you do need to build interface files, do so as follows:

- Download the [pygtk_to_pi.py](#) script and the [PyGTK sources](#) for your version of PyGTK if you don't already have them.

- Run as described within the script to produce a `*.pi` file for each `*.so` or `*.pyd` file in the PyGTK sources.
- Copy these `*.pi` files into the installed copy of PyGTK, so they sit next to the compiled `*.so` or `*.pyd` extension module file that they describe.
- Wing should now provide auto-completion and (in Wing IDE Pro) Source Assistant information when you `import gtk` and type `gtk.` in the editor.

With newer PyGTK versions, it may be necessary to make modifications to the `pygtk_to_pi.py` script to track changes in the nature of the source base.

Using a GUI Builder

Wing IDE doesn't currently include a GUI builder for PyGTK but it can be used with other tools, such as [glade](#).

To use an external GUI builder, **configure Wing to automatically reload files** that are altered by the GUI builder. This is done in Preferences in the **Files / Reloading** area.

Then you can run Wing IDE and your GUI builder at the same time, working with both in an almost seamless manner.

A Caveat: Because Python lends itself so well to writing data-driven code, you may want to reconsider using a GUI builder for some tasks. In many cases, Python's introspection features make it possible to write generic GUI code that you can use to build user interfaces on the fly based on models of your data and your application. This can be much more efficient than using a GUI builder to craft individual menus and dialogs by hand. In general hand-coded GUIs also tend to be more maintainable.

Details and Notes

- Building GTK from sources can be a challenge. Wingware has developed some build support scripts which we can provide on request. We also have patches that allow GTK to be relocated after building on Linux/Unix.
- Native look and feel on Windows is provided by the [gtk-wimp](#) theme. If you plan to deploy on Windows, you may wish to contact us to obtain our latest performance patches for GTK on Windows.

Unfortunately not all of our patches have been merged into the current GTK sources, although we have contributed patches in all cases so they can be retrieved from the source forge bug tracker as well.

Related Documents

Wing IDE provides many other options and tools. For more information:

- **Wing IDE Reference Manual**, which describes Wing IDE in detail.
- **Wing IDE Quickstart Guide** which contains additional basic information about getting started with Wing IDE.

5.3. Using Wing IDE with PyQt

[Wing IDE](#) is an integrated development environment for the Python programming language. Wing can be used to speed up the process of writing and debugging code that is written for the [PyQt](#) cross-platform GUI development toolkit.

PyQt is a commercial GUI development environment that runs with native look and feel on Windows, Linux/Unix, Mac OS, and the Sharp Zaurus. Commercial licensing is per developer, with no cost for each deployed product. It is also available for free for non-commercial users under the GPL license.

While Wing IDE does not currently provide a GUI builder for PyQt, it does provide the most advanced capabilities available for the Python programming language and it can be used with other available GUI builders, as described below.

Installation and Configuration

Take the following steps to set up and configure Wing IDE for use with PyQt:

- Install Python and Wing. Check the [PyQt download page](#) to make sure you install a version of Python that will work with the version of PyQt that you use. For example, PyQt 3.5 worked with any version of Python between 1.5.2 and 2.2.x. The generic **Wing IDE Quickstart Guide** provides installation instructions for Wing.
- Install Qt from [Trolltech](#). You will either need to purchase a developer's licence or download the non-commercial package.

- Install PyQt from the [Riverbank PyQt download area](#).
- Start Wing from the Start menu on Windows, the Finder or OS X, or by typing `wing-personal3.2` on the command line on Linux other Posix systems. Once Wing has started, you may want to switch to reading this How-To from the **Help** menu. This will add links to the functionality of the application.
- Select **Show Analysis Stats** from the Source menu and if the Python version reported there doesn't match the one you're using with PyQt, then select **Project Properties** from the Project menu and use the **Python Executable** field to select the correct Python version.
- Open `examples/tools/qtdemo/qtdemo.py` into Wing IDE (located within your Python installation) and select **Add Current File** from the Project menu.
- Set `qtdemo.py` as main entry point for debugging with **Set Main Debug File** in the Debug menu.
- Save your project to disk. Use a name ending in `.wpr`.

Test Driving the Debugger

Now you're ready to try out the debugger. To do this:

- Start debugging with the **Start / Continue** item in the Debug menu. Uncheck the **Show this dialog before each run** checkbox at the bottom of the dialog that appears and select **OK**.
- The demo application will start up. If its main window doesn't come to front, bring it to front from your task bar or window manager.
- Next open the source for one of the demos in Wing IDE and set a breakpoint in code that will be reached when you work with that demo. Exercise the demo so that the breakpoint is reached.
- Use the **Stack Data** tool in the **Tools** menu to look around the stack and the locals and globals for the selected stack frame.
- Select **Debug Probe** (Wing Pro only) from the **Tools** menu. This is an interactive command prompt that lets you type expressions or even change values in the context of the stack frame that is selected on the Debugger window when your program is paused or stopped at an exception. It is a very powerful debugging tool.

Also take a look at these tools available from the Tools menu:

- **I/O** -- displays debug process output and processes keyboard input to the debug process, if any
- **Exceptions** -- displays exceptions that occur in the debug process
- **Modules** (Wing Pro only) -- browses data for all modules in `sys.modules`
- **Watch** (Wing Pro only) -- watches values selected from other value views (by right-clicking and selecting one of the **Watch** items) and allows entering expressions to evaluate in the current stack frame

As you try out the various demos for PyQt, you may sometimes see Wing IDE pause and report exceptions in the debugger's **Exceptions** tool. There are a few bugs in some versions of PyQt's demos, so Wing will catch those when they occur.

Using a GUI Builder

Wing IDE doesn't currently include a GUI builder for PyQt but it can be used with other tools, such as [Black Adder](#), which does provide a GUI builder but doesn't have all of the features of Wing. Another GUI builder for PyQt is [Qt Designer](#), which outputs language-independent UI files that can be converted into Python using PyQt's `pyuic` utility.<P>

To use an external GUI builder, **configure Wing to automatically reload files** that are altered by the GUI builder. This is done in Preferences in the **Files Reloading** area.

Then you can run Wing IDE and your GUI builder at the same time, working with both in an almost seamless manner.

A Caveat: Because Python lends itself so well to writing data-driven code, you may want to reconsider using a GUI builder for some tasks. In many cases, Python's introspection features make it possible to write generic GUI code that you can use to build user interfaces on the fly based on models of your data and your application. This can be much more efficient than using a GUI builder to craft individual menus and dialogs by hand. In general hand-coded GUIs also tend to be more maintainable, and the Qt widget set was designed specifically to make hand-coding easy.

Tips for Keeping the Debug Process Responsive

Because of bugs in some versions of PyQt, there is no code inside the debugger to ensure that PyQt debug processes remains responsive to the debugger while free-running. This means that you may not always be able to Pause PyQt debug processes, and the debugger may time out if you try to add breakpoints or execute certain other debugger operations while the GUI application is free-running and no Python code is being reached.

This problem occurs only when no Python code is reached at all, so it is easy to work around with the following after your `QApplication` has been created and before you call `exec_loop()`:

```
# Hack to burn some Python bytecode periodically so Wing's
# debugger can remain responsive while free-running
import os
if os.environ.has_key('WINGDB_ACTIVE'):
    timer = QtCore.QTimer()
    def donothing(*args):
        x = 0
        for i in range(0, 100):
            x += i
    timer.connect(timer, QtCore.SIGNAL("timeout()"), donothing)
    timer.start(200)
```

Related Documents

Wing IDE provides many other options and tools. For more information:

- [Wing IDE Reference Manual](#), which describes Wing IDE in detail.
- [PyQt home page](#), which provides links to documentation.
- [Wing IDE Quickstart Guide](#) which contains additional basic information about getting started with Wing IDE.

5.4. Using Wing IDE with matplotlib

[Wing IDE](#) is an integrated development environment for the Python programming language. Wing can be used to speed up the process of writing and debugging code that is written for [matplotlib](#), a powerful 2D plotting library for Python.

Note: This document contains only matplotlib specific tips; see the **Wing IDE Manual** and **Tutorial** for more information.

Working in the Python Shell

Users of matplotlib often work interactively in the Python command line shell. For example, two plots could be shown in succession as follows:

```
from pylab import plot,show,close
x = range(10)
plot(x)
show() # This blocks until the plot window is closed manually
y = [2, 8, 3, 9, 4]
plot(y)
close()
```

When this is done in Wing's Python Shell, the `show()` will not return until the first window is closed and subsequent plots will not run interactively so their windows will fail to update if obscured and re-displayed. This happens because the main loop that services events for the plot windows is not being run.

To solve this problem, try using a `Timer` from Python's `threading` module for the `show()` call, as follows:

```
from threading import Timer
t = Timer(0, show)
t.start()
```

This has been tested on Windows with `numpy 1.2.1`, `scipy 0.7.0.b1`, and a `matplotlib 0.98.5.2` installation where `matplotlib.get_backend()` reports `TkAgg`. It may not work with other backends or on other OSes, although it may be possible to devise a similar technique for other backends by calling the GUI layer directly.

Related Documents

Wing IDE provides many other options and tools. For more information:

- **Wing IDE Reference Manual**, which describes Wing IDE in detail.
- [The matplotlib home page](#), which provides links to documentation.

- **Wing IDE Quickstart Guide** which contains additional basic information about getting started with Wing IDE.

How-Tos for Other Libraries

The following How-Tos provide tips and short cuts for using a number of other popular development frameworks with Wing IDE.

6.1. Using Wing IDE with Twisted

[Wing IDE](#) is an integrated development environment for the Python programming language. Wing can be used to speed up the process of writing and debugging code that is written for [Twisted](#).

Note: This document contains information obtained from users of Wing IDE. Its accuracy has not yet been verified by Wingware.

Installing Twisted

The [Twisted website](#) provides complete instructions for installing and using Twisted.

Debugging in Wing IDE

To debug Twisted code launched from within Wing IDE, create a file with the following contents and set it as your main debug file by adding it to your project and then using the Set Main Debug File item in the Debug menu:

```
from twisted.scripts.twistd import run
import os
try:
    os.unlink('twistd.pid')
except OSError:
    pass
```

```
run()
```

Then go into the **File Properties** for this file (by right clicking on it) and set **Run Arguments** to something like:

```
-n -y name.tac
```

The `-n` option tells Twisted not to daemonize, which would cause the debugger to fail because sub-processes are not automatically debugged. The `-y` option serves to point Twisted at your `.tac` file (replace `name.tac` with the correct name of your file instead).

You can also launch Twisted code from outside of Wing using the module `wingdbstub.py` that comes with Wing. This is described in **Debugging Externally Launched Code** in the manual.

Related Documents

Wing IDE provides many other options and tools. For more information:

- **Wing IDE Reference Manual**, which describes Wing IDE in detail.
- [Twisted home page](#), which provides links to documentation.
- **Wing IDE Quickstart Guide** which contains additional basic information about getting started with Wing IDE.

6.2. Using Wing IDE with Cygwin

[Wing IDE](#) is an integrated development environment for the Python programming language. Wing can be used to speed up the process of writing and debugging Python code that is written for [cygwin](#), a Linux/Unix like environment for Microsoft Windows.

Introduction

To write and debug code running under cygwin, download and install Wing IDE for Windows on your machine. There is no Wing IDE for cygwin specifically but you can set up Wing IDE for Windows to work with Python code that is running under cygwin.

Cygwin has a different view of the file system than the paths used by Windows applications. This causes problems when code is debugged since Wing cannot find the files referenced by their cygwin name.

The solution to this problem is to treat Python running under cygwin as if it were running on a separate system. This is done using Wing's **external launch / remote debugging support**. In this model, you will always launch your Python code from cygwin rather than from Wing's menus or toolbar.

When setting this up according to the instructions provided by the above link, use cygwin paths when setting up WINGHOME in `wingdbstub.py`.

You will also need to set up a file location translation map from your cygwin names (usually by default something like `/c/path/to/files` maps to `C:\path\to\files`), or set things up in cygwin's configuration so that the cygwin pathname is equivalent to the win32 pathname. For the latter, an example would be to set up `/src` in cygwin to point to the same dir as `\src` in win32 (which is `src` at top level of the main drive, usually `c:\src`). Wing will ignore the difference between forward and backward slashes in path names.

Related Documents

Wing IDE provides many other options and tools. For more information:

- **Wing IDE Reference Manual**, which describes Wing IDE in detail.
- [Cygwin home page](#), which provides links to documentation.
- **Wing IDE Quickstart Guide** which contains additional basic information about getting started with Wing IDE.

6.3. Using Wing IDE with pygame

[Wing IDE](#) is an integrated development environment for the Python programming language. Wing can be used to speed up the process of writing and debugging code that is written for [pygame](#), an open source framework for game development with Python..

To get started, refer to the tutorial in the **Help** menu in Wing and/or the **Wing IDE Quickstart Guide**.

Debugging pygame

You should be able to debug pygame code with Wing just by starting debug from the IDE. However, some versions of pygame running in full screen mode may not work properly and may crash Wing. If that is the case, use window mode instead while debugging.

This problem exists with other Python IDEs as well; we have not yet determined what the cause is and it appears to have been fixed in newer pygame versions.

Related Documents

Wing IDE provides many other options and tools. For more information:

- **Wing IDE Reference Manual**, which describes Wing IDE in detail.
- **Wing IDE Quickstart Guide** which contains additional basic information about getting started with Wing IDE.

6.4. Using Wing IDE with Blender

[Wing IDE](#) is an integrated development environment for the Python programming language. Wing can be used to speed up the process of writing and debugging Python code that is written for [Blender](#), an open source 3D content creation system.

Introduction

Blender's loads Python scripts in a way that makes them difficult to debug in a Python debugger. The following stub file can be used to work around these problems:

```
import os
import sys

# MODIFY THESE:
winghome = r'c:\Program Files\Wing IDE 2.1'
scriptfile = r'c:\src\test\blender.py'

os.environ['WINGHOME'] = winghome
```

```

if winghome not in sys.path:
    sys.path.append(winghome)
#os.environ['WINGDB_LOGFILE'] = r'c:\src\blender-debug.log'
import wingdbstub
wingdbstub.debugger.StartDebug()

def runfile(filename):
    execfile(filename)
runfile(scriptfile)

```

To use this script:

- 1) Modify `winghome` & `scriptfile` definitions where indicated to the wing installation directory and the script you want to debug, respectively. When in doubt, the location to use for `winghome` is given as the **Install Directory** in your Wing IDE About box (accessed from **Help** menu).
- 2) Run blender
- 3) Click on upper left icon and select text editor
- 4) Click on icon to right of “File” to display text editor pane
- 5) Select File -> Open from the *bottom* menu bar and select this file to open

Once the above is done you can debug your script by executing this `blenderstub` file in blender. This is done using File -> Run Python Script from the bottom menu or by the Alt-P key, though Alt-P seems to be sensitive to how the focus is set.

Note that you will need to turn on passive listening for debug connections in Wing, which is most easily done by clicking on the bug icon in the lower left of the main window and selecting **Enable Passive Listen** in the popup menu that appears.

Related Documents

Wing IDE provides many other options and tools. For more information:

- **Wing IDE Reference Manual**, which describes Wing IDE in detail.
- [Blender home page](#), which provides links to documentation.
- **Wing IDE Quickstart Guide** which contains additional basic information about getting started with Wing IDE.

6.5. Using Wing IDE with scons

[Wing IDE](#) is an integrated development environment for the Python programming language. Wing can be used to speed up the process of writing and debugging code that is written for [scons](#), an open source software construction or build control framework that uses Python.

To get started, refer to the tutorial in the **Help** menu in Wing and/or the **Wing IDE Quickstart Guide**.

Debugging scons

As of version 0.96.1 of `scons`, the way that `scons` executes build control scripts does not work properly with any Python debugger because the scripts are executed in an environment that effectively sets the wrong file name for the script. Wing will bring up the wrong file on exceptions and will fail to stop on breakpoints.

The solution for this is to patch `scons` by replacing the `exec _file_` call with one that unsets the incorrect file name, so that Wing's debugger looks into the correctly set `co_filename` in the code objects instead.

The code to replace is in `engine/SCons/Script/SConscript.py` (around line 239 in `scons` version 0.96.1):

```
exec _file_ in stack[-1].globals
```

Here is the replacement code to use:

```
old_file = call_stack[-1].globals.pop('__file__', None)
try:
    exec _file_ in call_stack[-1].globals
finally:
    if old_file is not None:
        call_stack[-1].globals.update({'__file__':old_file})
```

Once this is done, Wing should show the correct file on exceptions and stop on breakpoints set within the IDE.

Note that if you launch `scons` from the command line (likely the preferred method) rather than from within Wing IDE, you will need to use `wingdbstub` to initiate debugging, as described in **Debugging Externally Launched Code**.

Related Documents

Wing IDE provides many other options and tools. For more information:

- **Wing IDE Reference Manual**, which describes Wing IDE in detail.
- **Wing IDE Quickstart Guide** which contains additional basic information about getting started with Wing IDE.

6.6. Handling Large Values and Strings in the Debugger

To avoid hanging up on large values during stepping and other debugger actions, the debugger limits the size of constructs that it will display.

You can alter the size limit on large compound values with the **Huge List Threshold** preference. If you do this, you may also need to increase the debugger's patience in waiting for these large lists to transfer with the **Network Timeout** preference.

Long strings are also truncated by default when they are sent to the IDE from the debug process. The maximum displayable length of strings is controlled with the **Huge String Threshold** preference.

To view all of a truncated string, right click on them in the Stack Data tool and select **Show Detail** from the popup that appears. Alternatively in Wing Professional you can use the Debug Probe or Watch tools, accessible from the Tools menu. For example, for a large array, you can enter a value like `a[2:5] [7]` to arrive at a manageable value size.

6.7. Debugging C/C++ and Python together

Wing's debugger is for Python code only and doesn't itself handle stepping into C or C++. However, you can set up VC++ or the gdb debugger in conjunction with the Wing IDE debugger to debug errors in either C or Python at the same time.

This can be done either by launching the debug process from Wing and attaching the C/C++ debugger to it, or by launching the debug process with the C/C++ debugger and then initiating debug in Wing by importing `wingdbstub` in your Python code. To configure `wingdbstub`, see the manual section on **Debugging Externally Launched Code**.

To debug the C/C++ code you need to be running with a copy of Python compiled from sources with debug symbols.

See also this additional information on **using gdb and Wing together**. Using Wing and VC++ is prone to fewer problems and doesn't currently have its own How-To.

6.8. Debugging Extension Modules on Linux/Unix

Gdb can be used as a tool to aid in debugging C/C++ extension modules written for Python, while also running code in Wing's Python debugger.

This section assumes you are already familiar with gdb; for more information on gdb commands, please refer to the gdb documentation.

Preparing Python

The first step in debugging C/C++ modules with gdb is to make sure that you are using a version of Python that was compiled with debug symbols. To do this, you need a source distribution of Python and you need to configure the distribution as described in the accompanying README file.

In most cases, this can be done as follows: (1) Type `./configure`, (2) type `make OPT=-g` or edit the Makefile to add `OPT=-g`, and (3) type `make`. Once the build is complete you can optionally install it with `make install` (see the README first if you don't want to install into `/usr/local/lib/python`) but you can also run Python in place without installing it.

When this is complete, compile your extension module against that version of Python.

Starting Debug

In order to run code both within Wing's Python debugger and gdb, launch your debug process from Wing first, then note the process ID shown in the tooltip that appears when you hover the mouse over the debug icon in the lower left of Wing's main window.

Next, start gdb. First running `emacs` and then typing `Esc-X gdb` within emacs is one way of doing this, and this makes it easier to set breakpoints and view code as you go up and down the stack or step through it.

Within gdb, type `attach <pid>` where `<pid>` is replaced with the process ID reported by Wing. This will pause the process as it attaches, which gives you a chance to set

breakpoints (in `emacs` you can do this with `Ctrl-X Space` while working in the editor). When you're ready to continue the process, type `c` in `gdb`.

You are now debugging both at the Python and C/C++ level. You should be able to pause, step, and view data in Wing whenever `gdb` is not paused. When `gdb` is paused, Wing's debugger cannot be used until the process is continued at the `gdb` level.

Tips and Tricks

(1) You may want to set up your `~/.gdbinit` file by copying the contents of the file `Misc/gdbinit` from the Python source distribution. This contains some useful macros for inspecting Python code from `gdb` (for example `pystack` will print the Python stack, `pylocals` will print the Python locals, and `pyframe` prints the current Python stack frame)

(2) Note that breakpoints in a shared library cannot be set until after the shared library is loaded. If running your program triggers loading of your extension module library, you can use `^C^C` to interrupt the debug program, set breakpoints, and then continue. Otherwise, you must continue running your program until the extension module is loaded. When in doubt, add a `print` statement at point of import, or you can set a breakpoint at `PyImport_AddModule` (this can be set after `file python` and before running since this call is not in a shared library).

(3) For viewing Python data from the C/C++ side when using `gdb`. The following `gdb` command will print out the contents of a `PyObject *` called `obj` as if you had issued the command `print obj` from within the Python language:

```
(gdb) p PyObject_Print (obj, stderr, 0)
```

For more information see [Debugging with Gdb](#) in the Python wiki.

(4) If you are launching code in a way that requires you to set `LD_LIBRARY_PATH` and this is not working, check whether this value is set in `.cshrc`. This file is read each time `gdb` runs so may overwrite your value. To work around this, set `LD_LIBRARY_PATH` in `.profile` instead. This file is read only once at login time.

(5) Some older versions of `gdb` will get confused if you load and unload shared libraries repeatedly during a single debug session. You can usually re-run Python 5-10 times but subsequently may see crashing, failure to stop at breakpoints, or other odd behaviors. When this occurs, there is no alternative but to exit and restart `gdb`.

6.9. Debugging Code with XGrab* Calls

Under X11 (Linux/Unix), Wing does not attempt to break XGrabPointer or XGrabKey and similar resource grabs when your debug process pauses. This means that X may be unresponsive to the keyboard or mouse or both in some debugging cases.

Fixing the debugger to detect and ungrab resources in this case is quite difficult and prone to confusing and unwanted behaviors. Here are some tips for working around this problem:

(1) Some toolkits have an option to disable resource grabs specifically to avoid this problem during debugging. For example, PyQt has a command line option `-nograb` that prevents it from ever grabbing the keyboard or pointer. Adding this to the debug process command line solves the problem.

If you are writing your own calls to XGrab* or similar functions, consider adding a mode where these calls are skipped.

One trick that often helps is to move processing from the callback where the pointer or keyboard grab is still in effect into an asynchronous call-back that occurs at idle time. For example, under GTK use `gtk_idle_add()` and in wxPython try a `wxTimer`.

(2) Under XFree 4.2 and later, there is a configuration option you can set so that Ctrl-Alt-Keypad-/ will break through any active pointer and keyboard grabs:

```
# Let user break server grabs with ctrl-alt-keypad-/
Option "AllowDeactivateGrabs" "true"
```

This goes into your XF86Config file in the “ServerOptions” section. Check `man XF86Config` for the search path that X uses to find the config file and find the one that’s used on your system. For example, on Mandrake 8.2 the config file is `/etc/X11/XF86Config-4`.

You will need to restart your X server for the config changes to take effect (for example, log out and back in again). Be aware that altering your XF86Config file can cause X to fail to start up. If this happens, you will need to fix it in text mode. If you get into this situation, typing `startx` after each edit is a good way to check whether your fix works.

If you need to check what version of XFree you’re running, typing `rpm -q XFree86` usually works or `man XFree86` shows the version number at the very end of the man page.

(3) On Linux, if all else fails, you can use Ctrl-Alt-F1 through Ctrl-Alt-F6 on most distributions to get at six text-only virtual console. From there you can `ps` to find the

debug process and kill it with `kill -TERM` or `kill -9` if necessary. This will unlock your X windows display, which you can return to with `Ctrl-Alt-F7`.

(4) Displaying your debug process to another screen avoids tying up Wing in this way. Most servers will unlock the screen once you kill the debug process from Wing.

6.10. Debugging Non-Python Mainloops

Because of the way the Python interpreter supports debugging, the debug process may become unresponsive if your debug process is free-running for long periods of time in non-Python code, such as C or C++. Whenever the Python interpreter is not called for long periods of time, messages from Wing IDE may be entirely ignored and the IDE may disconnect from the debug process. This primarily affects pausing a free-running program or setting, deleting, or editing breakpoints while free-running.

Examples of environments that can spend significant amounts of time outside of the Python interpreter include GUI kits such as Gtk, Qt, Tkinter, wxPython, and some web development tools like Zope. For the purposes of this section, we call these “non-Python mainloops”.

Supported Non-Python Mainloops

Wing already supports Gtk, Tkinter, wxPython, and Zope. If you are using one of these, or you aren't using a non-Python mainloop at all, then you do not need to read further in this section.

Working with Non-Python Mainloops

If you are using an unsupported non-Python mainloop that normally doesn't call Python code for longer periods of time, you can work around the problem by adding code to your application that causes Python code to be called periodically. For an example, see the **PyQt How-To**. Similar code can be crafted in most non-Python mainloop environments.

The alternative to altering your code is to write special plug-in support for the Wing debugger that causes the debug server sockets to be serviced even when your debug program is free-running in non-Python code. The rest of this section describes what you need to know in order to do this.

Non-Python Mainloop Internals

Wing uses a network connection between the debug server (the debug process) and the debug client (Wing IDE) to control the debug process from the IDE and to inform

the IDE when events (such as reaching a breakpoint or exception) occur in the debug process.

As long as the debug program is paused or stopped at a breakpoint or exception, the debugger remains in control and it can respond to requests from the IDE. Once the debug program is running, however, the debugger itself is only called as long as Python code is being executed by the interpreter.

This is usually not a problem because most running Python program are executing a lot of Python code. However, in a non-Python mainloop, the program may remain entirely in C, C++, or another language and not call the Python interpreter at all for long periods of time. As a result, the debugger does not get a chance to service requests from the IDE. Pause or attach requests and new breakpoints may be completely ignored in this case, and the IDE may detach from the debug process because it is unresponsive.

Wing deals with this by installing its network sockets into each of the supported non-Python mainloops, when they are detected as present in the debug program. Once the sockets are registered, the non-Python mainloop will call back into Python code whenever there are network requests pending.

Supporting Non-Python Mainloops

For those using an unsupported non-Python mainloop, Wing provides an API for adding the hooks necessary to ensure that the debugger's network sockets are serviced at all times.

If you wish to write support for a non-Python mainloop, you first need to check whether there is any hope of registering the debugger's socket in that environment. Any mainloop that already calls UNIX/BSD sockets `select()` and is designed for extensible socket registration will work and is easy to support. Gtk and Zope both fell into this category.

In other cases, it may be necessary to write your own `select()` call and to trick the mainloop into calling that periodically. This is how the Tkinter and wxPython hooks work. Some environments may additionally require writing some non-Python glue code if the environment is not already set up to call back into Python code.

Mainloop hooks are written as separate modules that are placed into `src/debug/tserver` within `WINGHOME`. The module `_extensions.py` also found there includes a generic class that defines the API functions required of each module, and is the place where new modules must be registered (in the constant `kSupportedMainloops`).

Writing Non-Python Mainloop Support

To add your own non-Python mainloop support, you need to:

- 1) Copy one of the source examples (such as `_gtkhooks.py`) found in

`src/debug/server`, as a framework for writing your hooks. Name your module something like `_xxxxhooks.py` where `xxxx` is the name of your non-Python mainloop environment.

- 2) Implement the `_Setup()`, `RegisterSocket()`, and `UnregisterSocket()` methods. Do not alter any code from the examples except the code with in the methods. The name of the classes and constants at the top level of the file must remain the same.
- 3) Add the name of your module, minus the `.py` to the list `kSupportedMainloops` in `_extensions.py`

Examples of existing support hooks for non-Python mainloops can be found in `src/debug/tserver` within `WINGHOME`.

If you have difficulties writing your non-Python mainloop hooks, please contact Technical Support via <http://wingware.com/support>. We will be happy to assist you, and welcome the contribution of any hooks you may write.

6.11. Debugging Code Running Under Py2exe

Sometimes it is useful to debug Python code launched by an application produced by `py2exe` -- for example, to solve a problem only seen when the code has been packaged by "py2exe", or so that users of the packaged application can debug Python scripts that they write for the app.

When `py2exe` produces the `*.exe`, it strips out all but the modules it thinks will be needed by the application and may miss any required by scripts added after the fact. Also, `py2exe` runs in a slightly modified environment (for example the `PYTHONPATH` environment is ignored). Both of these can cause problems for Wing's debugger, but can be worked around with some modifications to the packaged code, as illustrated in the following example:

```
# Add extra environment needed by Wing's debugger
import sys
import os
extra = os.environ.get('EXTRA_PYTHONPATH')
if extra:
    sys.path.extend(extra.split(os.pathsep))
print sys.path

# Start debugging
```

```
import wingdbstub

# Just some test code
print "Hello from py2exe"
print "frozen", repr(getattr(sys, "frozen", None))
print "sys.path", sys.path
print "sys.executable", sys.executable
print "sys.prefix", sys.prefix
print "sys.argv", sys.argv
```

You will need to set the following environment variables before launching the packaged application:

```
EXTRA_PYTHONPATH=\Python25\Lib\site-
packages\py2exe\samples\simple\dist;\Python25\lib;\Python25\dlls
WINGDB_EXITONFAILURE=1
WINGHOME=\Program Files\Wing IDE 2.1
```

To debug, an installation of Python matching the one used by py2exe must be present and referenced by the `EXTRA_PYTHONPATH` environment variable. This example assumes the installation of Python 2.5 at `\Python25` was used by py2exe.

The directory `\Python25\Lib\site-packages\py2exe\samples\simple\dist` is where `wingdbstub.py` was placed; this can be altered as desired. Also, `WINGHOME` should be altered to match the location where Wing is installed and isn't needed at all if the value set in `wingdbstub.py` is correct (which it usually will be if copied out of the Wing installation).

When trying this out, be sure to **Enable Passive Listen** in Wing IDE by clicking on the bug icon in the lower left of the main window. For more information on using `wingdbstub` to debug, see **Debugging Externally Launched Code**

Enabling End Users to Debug

The above example is geared at the primary developers trying to find bugs in packaged code. If the packaged application is one that allows the end user to write add-on scripts and they want to debug these in Wing's debugger, then the `import wingdbstub` in the above example should be replaced with the following imports:

```
import socket
import select
import traceback
import struct
import cPickle
```

```
import site
import string
```

This forces `py2exe` to bundle the modules needed by Wing's debugger with the `.exe`, so that the end user can place `include wingdbstub` in their scripts instead.

Of course it's also possible to conditionally include the `import wingdbstub` in the main code, based on an environment variable or checking user settings in some other way. For example:

```
import os
if os.environ.has_key('USE_WING_DEBUGGER'):
    import wingdbstub
```

A combination of the above techniques can be used to craft debugging support appropriate to your particular `py2exe` packaged application.

The above was tested with `py2exe` run with `-q` and `-b2` options.